

DDC FILE COPY

ADA0 65406

97R-78-268-VOL-3

-	REPORT DOCUMENTATION PAGE	READ INSTRUCTIONS BEFORE COMPLETING FORM
(18)	RADC-TR-78-268, Vol III (of three)	PECIPIENT'S CATALOG NUMBER
0	FORTRAN AUTOMATED VERIFICATION SYSTEM (FAVS)	Final Zechnical Aspect, Oct 76 — Jan 78
	(Volume II.)	N/A
ich	A. Melton M. Andrews	F30602-76-C-0436
	General Research Corporation P.O. Box 6770 Santa Barbara CA 93111	10. PROGRAM ELEMENT, PROJECT, TASK AREA & WORK UNIT NUMBERS 63701B 32010320
	Rome Air Development Center (ISIE) Griffiss AFB NY 13441	January 1979
	14. MONITORING AGENCY NAME & ADDRESS(1) Millerent from Controlling Office) Same	15. SECURITY CLASS. (of this report) UNCLASSIFIED
		15a. DECLASSIFICATION/DOWNGRADING
	16. DISTRIBUTION STATEMENT (of this Report) Approved for public release; distribution unlimite	N/A
		DDC
	Approved for public release; distribution unlimite 17. DISTRIBUTION STATEMENT (of the abstract entered in Block 20, if different from	DDC om Report)
	Approved for public release; distribution unlimite 17. DISTRIBUTION STATEMENT (of the abstract entered in Block 20, if different for Same 18. SUPPLEMENTARY NOTES	DDC om Report) MAR 8 1979 B

UNCLASSIFIED

SECURITY CLASSIFICATION OF THIS PAGE (When Date Entered)











SECURITY CLASSIFICATION OF THIS PAGE(When Date Entered)

Item 20 (Cont'd)

evaluated and then compared with integers in a list of CASE statements that follow. Execution of a group of statements following the matching CASE statement is then initiated. The DMATRAN language also contains an INVOKE...BLOCK... END BLOCK construct which provides a form of internal subroutine capability as well as a way to reduce overhead costs by eliminating duplicate sections of code.

This DMATRAN User's Guide describes and illustrates each structured construct. It also explains how to use the DMATRAN precompiler which translates DMATRAN into compilable FORTRAN code. The DMATRAN precompiler provides additional source text editing and display features including page ejection, suppressing source listing, and changing the syntax of DMATRAN statements; the DMATRAN commands for these capabilities are also described.

The DMATRAN precompiler has been installed on the HIS 6180 GCOS and MULTICS computer systems at the Rome Air Development Center, Griffiss AFB, New York, and on the UNIVAC 1100/42 computer systems at the Defense Mapping Agency Aerospace Center in St. Louis, Missouri, and the Defense Mapping Agency Topographic Center in Washington, D.C.

ACCESSION	for
NTIS	White Section
DDC	Buff Section
UNANED	CEO D
JUSTI	/22
DISTRIB	AND ARREST CODES
Dist.	The court of SPECIME
A	

CONTENTS

SECTION		PAGE
1-1	INTRODUCTION	1-1
2	DMATRAN CONTROL CONSTRUCTS	2-1
	2.1 IFTHENELSEEND IF	2-3
	2.2 DO WHILEEND WHILE	2-5
	2.3 DO UNTILEND UNTIL	2-5
	2.4 CASE OFCASECASE ELSEEND CASE	2-8
	2.5 BLOCKEND BLOCK AND INVOKE	2-11
3	USING THE DMATRAN PRECOMPILER	3-1
	3.1 DMATRAN Input	3-1
	3.2 DMATRAN Indented Listing	3-2
	3.3 FORTRAN Output	3-3
4	DMATRAN CONSTRAINTS	4-1
	4.1 SYNTAX	4-1
	4.2 DO UNTIL	4-1
	4.3 CASE	4-1
	4.4 BLOCK Construct	4-1
5	DISPLAY COMMANDS	5-1
	5.1 Command Form	5-1
	5.2 Source Listing	5-2
	5.3 Double-Space Around Comments	5-2
	5.4 Keyword Recognition	5-2
	5.5 Page Ejection	5-5
	5.6 Extended Comment	5-5

CONTENTS CONT.

SECTION		PAGE
APPENDIX A	SUMMARY OF DMATRAN STATEMENTS AND COMMANDS	A-1
APPENDIX B	FILE DESCRIPTIONS	B-1
APPENDIX C	JOB STREAMS	C-1
	INDEX . Permanental Language was week	I-1

ILLUSTRATIONS

	PAGE
DMATRAN Precompiler	1-2
DMATRAN Control Constructs	2-2
IFTHENEND IF Construct	2-3
IFTHENELSEEND IF Construct	2-4
DO WHILEEND WHILE Construct	2-6
DO UNTILEND UNTIL	2-7
CASE OFCASECASE ELSEEND CASE	2-9
DMATRAN Case Construct	2-10
BLOCKEND BLOCK and INVOKE Construct	2-12
BLOCK Cross-Reference Report	2-13
DMATRAN Source Input	3-1
DMATRAN Indented Listing	3-2
Translated FORTRAN	3-4
DMATRAN Keyword Syntax	5-3
Listing of DMATRAN Keyword Example	5-4

1 INTRODUCTION

DMATRAN is an extension to FORTRAN that simplifies structured programming by providing a convenient syntax for writing structured programming control constructs. The DMATRAN precompiler translates the DMATRAN statements into standard FORTRAN while passing all other statements unchanged to a file which can then be compiled by the FORTRAN compiler. This sequence is illustrated in Fig. 1.1. In addition to the translation, the precompiler checks the control structure for proper use of DMATRAN control structures and issues error messages if violations occur.

The precompiler provides the following additional features to improve code production:

- 1. Indented listing of the DMATRAN source code.
- Editing functions which include in-line comments, doublespacing around comments, indentation control, selective page ejection, and selective suppression of the source listings.




Figure 1.1. DMATRAN Precompiler

2 DMATRAN CONTROL CONSTRUCTS

DMATRAN replaces FORTRAN control statements with the following control statement constructs:

- IF...THEN...ELSE...END IF provides block structuring of conditionally executable sequences of statements.
- DO WHILE...END WHILE permits iteration of a code segment while a specified condition remains true.
- CASE OF...CASE...CASE ELSE...END CASE allows multiple choices for program action selection.
- DO UNTIL...END UNTIL permits iteration until a specified condition becomes true.
- INVOKE<name>...BLOCK<name>...END BLOCK provides a facility
 for top-down programming and internal subroutines.

These statement forms can be intermixed with ordinary FORTRAN non-control statements in the text stream which is processed by the DMATRAN precompiler. DMATRAN statements are converted by the precompiler to equivalent FORTRAN statements, and the resulting file can be compiled by the FORTRAN compiler in the normal manner. A description, flowchart, and example of each DMATRAN control construct is provided in this section. The DMATRAN constructs are shown in Fig. 2.1.

Esquire 2.1. Bearman Copyrol Comstructs




Figure 2.1. DMATRAN Control Constructs

2.1 IF...THEN...ELSE...END IF

The IF...THEN...ELSE...END IF construct provides block structuring of conditionally executable statements. The basic form of this construct is IF...THEN...END IF, illustrated in Fig. 2.2. If <expression> is true, control transfers to the first statement within the construct; otherwise, the statement immediately following the END IF will be executed. Use of the ELSE statement is optional. If the ELSE is present and <expression> is false, the statements following the ELSE are executed. This construct is illustrated in Fig. 2.3.

IF (<EXPRESSION>) THEN

STATEMENTS TO EXECUTE IF <EXPRESSION> IS TRUE
END IF




Figure 2.2. IF...THEN...END IF Construct


IF (<EXPRESSION>) THEN

STATEMENTS TO EXECUTE IF <EXPRESSION> IS TRUE

ELSE

. STATEMENTS TO EXECUTE IF <EXPRESSION> IS FALSE

END IF The St des and indeed for the become



FUNCTION SINC(X)
IF (X .EQ. 0) THEN
. SINC = 1.
ELSE
. SINC = SIN(X)/X
END IF
RETURN
END

Figure 2.3. IF...THEN...ELSE...END IF Construct

2.2 DO WHILE...END WHILE

The DO WHILE...END WHILE construct indicates a repetitive operation which is to be performed zero or more times. Execution occurs in the following manner:

- The value of <expression> is found: if true, the statements contained within the DO WHILE block are executed; if false, control passes to the statement immediately following the END WHILE.
- 2. If the statements within the DO WHILE block have been executed, the value of <expression> is checked again, with the same consequences as in (1).

Figure 2.4 illustrates the form and meaning of this construct. It is important to note that no initialization or incrementing operations are caused by the DO WHILE...END WHILE construct. Initialization must be explicitly performed prior to entering the loop, and the iteration variables must be explicitly modified on each pass through the loop.

2.3 DO UNTIL...END UNTIL

The DO UNTIL...END UNTIL construct is like a FORTRAN DO-LOOP in that it is performed at least once and has a single exit at the bottom of the loop, and like a DO WHILE...END WHILE in that no initialization or incrementing operations are caused by this construct. Initialization must be performed prior to entering the loop, and iteration variables must be modified on each pass through the loop. Figure 2.5 illustrates this construct.

The statements enclosed within the DO UNTIL and the END UNTIL are executed at least once. Then <expression> is evaluated and, if false, iteration and evaluation of the expression continue until it is true. At that time execution of the statements following the END UNTIL begins.

INITIALIZATION STATEMENTS

DO WHILE (<EXPRESSION>)

STATEMENTS TO EXECUTE IF <EXPRESSION> IS TRUE

END WHILE





Figure 2.4. DO WHILE...END WHILE Construct

INITIALIZATION STATEMENTS

DO UNTIL (<EXPRESSION>)

STATEMENTS TO EXECUTE IF <EXPRESSION > IS FALSE

END UNTIL



```
FUNCTION CONVRG(XINIT, EPS, F)
EXTERNAL F
X = XINIT
DO UNTIL (ABS(X-XOLD).LE.EPS)
. XOLD = X
. X = F(X)
END UNTIL
CONVRG = X
RETURN
END
```

Figure 2.5. DO UNTIL... END UNTIL

2.4 CASE OF...CASE...CASE ELSE...END CASE

The CASE statement provides a way to select which group of statements will be executed. The general form of the CASE construct consists of CASE OF...CASE...CASE ELSE...END CASE.

Figure 2.6 illustrates the CASE construct. I, J, and N represent integers of positive value. They may be in any order, and there is no limit to how many integers may be listed.

The value of <integer expression> is computed, and if any of the specified integers in the CASE list are equal to the value of <expression> then the transfer of control is to the statements which follow that particular CASE. If there is no such CASE, and the CASE ELSE statement is present, then the block of statements following the CASE ELSE is executed; otherwise, no block is executed. If there are two CASE statements with the same CASE index, then the block of statements following the first occurring one is executed (if the CASE expression has that value). After the block of statements selected has been executed, control transfers to the statement after the END CASE.

A listing containing an example of the CASE construct is shown in Fig. 2.7.

CASE OF (<INTEGER EXPRESSION>)

CASE (I)

BLOCK OF STATEMENTS

CASE (J)

BLOCK OF STATEMENTS

CASE (N)

BLOCK OF STATEMENTS

CASE ELSE

BLOCK OF STATEMENTS




Figure 2.6. CASE OF .. CASE .. CASE ELSE ... END CASE

```
SUBROUTINE XAMPL (ITYPE, NPARS)

CASE OF (ITYPE)

CASE (3)

CALL GETCRD(ITYPE)

CASE (5)

JTYPE = ITYPE + 3

CALL STRUCT(JTYPE)

CASE (9)

CALL IBALPR(ITYPE, NPARS)

CASE ELSE

CALL ERROR

END CASE

RETURN
```

Figure 2.7. DMATRAN Case Construct

END

2.5 BLOCK...END BLOCK and INVOKE

The BLOCK...END BLOCK construct provides a form of internal subroutine capability in DMATRAN source programs. This construct is an
internal procedure which has access to all variables in the routine
which contains it. A BLOCK...END BLOCK is executed only if it is
referred to with an INVOKE statement which specifies its name. The
form for this construct is:

INVOKE (<name>)
:
BLOCK (<name>)
:
END BLOCK

where <name> is any string of characters (i.e., COMPUTE LENGTH, PRINT CURRENT STATUS, or COMPUTE NEW ARRAY ELEMENT). The name of a BLOCK may be arbitrarily long, so that the name can have mnemonic significance. All characters are significant after the first non-blank and before the last non-blank. The name of a BLOCK is known throughout the entire routine in which it is contained. Figure 2.8 illustrates this construct.

As the flowchart for this construct indicates, it is a single-entry (the BLOCK statement), single-exit (the END BLOCK statement) section of code. An INVOKE statement causes control to transfer to the named BLOCK statement, and the matching END BLOCK statement causes control to transfer back to the statement after the INVOKE. More than one INVOKE for a given BLOCK...END BLOCK construct is allowed. Though BLOCK...END BLOCK constructs can be nested, no recursion is allowed in the invoking of BLOCKS (i.e., a BLOCK cannot directly or indirectly invoke itself). BLOCKS cannot be invoked from an external routine, nor can they be passed as a parameter to another routine. BLOCK constructs may be placed before or after the RETURN statement.

```
INVOKE (<NAME>)
BLOCK (<NAME>)
BLOCK STATEMENTS
BLOCK
```




Figure 2.8. BLOCK... END BLOCK and INVOKE Construct

When the BLOCK...END BLOCK construct is used, available space for storing additional BLOCK names is indicated in the BLOCK Cross-Reference Report (Fig. 2.9) which follows the DMATRAN source listing for each module. The total number of characters in all BLOCK names used in one subroutine cannot exceed 1,000. The number of INVOKEs and the number of BLOCKs varies with each module as it is dependent on the size of the names of the BLOCKs and the number of invocations. When the maximum has been reached, a message is printed on the DMATRAN listing indicating a BLOCK name table overflow.

BLOCK CROSS-REFERENCE

64
6

645 WORDS LEFT

Figure 2.9. BLOCK Cross-Reference Report

THIS PAGE IS BEST QUALITY PRACTICABLE FROM COPY PURMISHED TO DDC There are many reasons for using the BLOCK construct. For example, the overhead in calling subroutines is often very high; and, in addition, variables in FORTRAN and DMATRAN programs must be passed as parameters or placed in COMMON to be accessible to both the calling routine and the subroutine which is called. Often a subroutine references only variables which are already in the calling routine. Using a BLOCK structure as a internal subroutine eliminates the need to provide a means of accessing these variables.

Another way the BLOCK construct can improve overhead costs is by elimination of duplicate sections of code. Since the same BLOCK can be invoked by more than one INVOKE statement, code can be made more efficient by putting identical sections of code into BLOCK structures. The following example illustrates the use of BLOCKs to avoid code duplication.

 ${\rm S}_1$ and ${\rm S}_2$ in the following code represent two sets of statements. The use of a BLOCK in Method 2 below eliminates the need for duplicating code.

Method 1:

IF(A) THEN

IF(C) THEN

S₁

S,

END IF

ELSE

IF(D) THEN

S

ELSE

S1

END IF

END IF

Method 2:

IF(A) THEN

IF(C) THEN

INVOKE (BLOCK-A)

ELSE

INVOKE (BLOCK-B)

END IF

ELSE

IF(D) THEN

INVOKE (BLOCK-B)

ELSE

INVOKE (BLOCK-A)

END IF

END IF

where the BLOCKs are defined as:

BLOCK (BLOCK-A)

Sı

END BLOCK

and

BLOCK (BLOCK-B)

S₂

END BLOCK

3 USING THE DMATRAN PREPROCESSOR

3.1 DMATRAN INPUT

Figure 3.1 illustrates a DMATRAN source program with embedded FORTRAN statements ready for input to the DMATRAN precompiler. The DMATRAN source code begins in column 7 and is not indented. More than one module may be processed in each DMATRAN run.

	SUBROUTINE EXAMPL (INFC.LENGTH)	EXAMPL1
C		EXAMPL2
C	ILLUSTRATION OF DMATRAN SYNTAX	EXAMPL3
C		EXAMPL4
	IF (INFO.LE.10 .AND. LENGTH.GT.O) THEN	EXAMPLS
	CALL CALLER (INFO)	EXAMPL6
	ELSE	EXAMPL7
	LENGTH=50	EXAMPLE
	ENC IF	EXAMPL9
	CASE OF (INFO+6)	EXAMPL10
	CASE (14)	EXAMPL11
	LENGTH=LENGTH-INFO	EXAMPL12
	CASE (17)	EXAMPL13
	DO WHILE (INFO.LT.20)	EXAMPL14
	DO UNTIL (LENGTH.LE.INFO)	EXAMPL15
	INVOKE (COMPUTE LENGTH)	EXAMPL16
	IF (LENGTH.GE.30) THEN	EXAMPL17
	INVOKE (PRINT-RESULTS)	EXAMPL18
	END IF	EXAMPL19
	END UNTIL	EXAMPL20
	INFC=INFO+1	EXAMPL21
	END WHILE	EXAMPL22
	CASE ELSE	EXAMPL23
	DO WHILE (LENGTH.GT.O)	EXAMPL24
	INVOKE (COMPUTE LENGTH)	EXAMPL25
	END WHILE	EXAMPL26
	END CASE	EXAMPL27
	BLOCK (PRINT-RESULTS)	EXAMPL28
	WRITE (6,1)INFC, LENGTH	EXAMPL29
	1 FORMAT (10x.15.20x.15)	EXAMPL30
	END BLOCK	EXAMPL31
	BLOCK (COMPUTE LENGTH)	EXAMPL 32
	LENGTH = LENGTH -10	EXAMPL33
	END BLOCK	EXAMPL34
	RETURN	EXAMPL35
	END	EXAMPL36

Figure 3.1. DMATRAN Source Input

THIS PAGE IS BEST QUALITY PRACTICABLE
FROM COPY FARMISHED TO DDC

3.2 DMATRAN INDENTED LISTING

Figure 3.2 illustrates the automatically indented DMATRAN listing which resulted from processing the input shown in Fig. 3.1. The heading contains information from the first card of the routine being processed, as well as a page number. The leftmost column of numbers refers to the successive statements of the DMATRAN source deck. The nesting depth of each indented statement is indicated next to the statement number. Structural visibility is enhanced by connecting related DMATRAN statements with vertical dots. The dots assist in tracing paths through the program, identifying the statement number for a given line, and debugging improperly formed DMATRAN control constructs. Structural errors are indicated by error diagnostics in the DMATRAN listing. Sequence information following column 72 of the DMATRAN source cards is included on the right side of the DMATRAN listing.

ES	NEST	SOURCE	SUBROUTINE EXAMPL (INFO:LENGTH)	PAGE	1
1			SUBROUTINE EXAMPL (INFO, LENGTH)	•	XAMPL
5		C			XANPL
3		C	ILLUSTRATION OF DMATRAN SYNTAX		AAPPL
4		C			XAMPL
5			IF (INFO.LE.10 .AND. LENGTH.GT.Q)THEN		XAMPL
6	1		. CALL CALLER (INFO)		XAMPL
7			ELSE		XAMPL
8	1		. LENGTH=50		XAPPL
9	5		END IF		XAPPL
10			CASE OF (INFC+6)		XAMPL
11			CASE (14)		AAMPL
12	1		. LENGTH=LENGTH-INFO	E	XAPPL
13			CASE (17)		XANPL
14	1		. DO WHILE (INFC-LT-20)		XANPL
15	2		CO UNTIL (LENGTH.LE.INFQ)		XAMPL
16	3		ILVOKE (COMPUTE LENGTH)		XAPPL
17	3		IF (LENGTH.GE.30) THEN		XAVPL
18	4		INVOKE (PRINT-RESULTS)		XAMPL
19	3		ENU 1F		MANPL
20	2		END UNTIL		XAMPL
21	2		INFC=INFO+1		XAMPL
22	1		. END WHILE		XAMPL
23			CASE ELSE		MANPL
24	1		. DO WHILE (LENGTH.GT.D)		XAPPL
25	2		INVOKE (COMPUTE LENGTH)		XAVEL
26	1		. END WHILE		MANPL
27			END CASE		XAMPL
56			BLOCK (PHINT-RESULTS)		XANPL
29	1		. WRITE (6.1) INFO. LENGTH		XAMPL
30	1	1	. FORFAT (10X.15.20X.15)		XANPL
31			END BLOCK		XAMPL
32			BLOCK (COPPUTE LENGTH)		XAMPL
33	1		. LENGTH = LENGTH -10		XAMPL
34			END BLUCK		XAMPL
35			KETUKN		AMPL
36			ENO		XAMPL

Figure 3.2. DMATRAN Indented Listing

MIS PAGE IS BEST QUALITY FRACTICABLE

3.3 FORTRAN OUTPUT

Figure 3.3 illustrates a portion of the FORTRAN translation produced by the DMATRAN precompiler. The input was the SUBROUTINE EXAMPL from Fig. 3.2. The information in columns 73 to 80 of the translated FORTRAN is useful for tracing translated FORTRAN statements back to the original DMATRAN source statements. If the original source statement was a FORTRAN statement, columns 73 and 74 will contain "FO"; if it was a DMATRAN statement, column 1 is a "C" and columns 73 and 74 contain "DM." In either case columns 77 through 80 contain the original DMATRAN source statement number (the leftmost column of numbers on the DMATRAN listing) and columns 75 and 76 contain the depth of nesting of the original statement.

THIS PAGE IS BEST QUALITY TRACTICABLE FROM COPY FURNISHED TO DDC

c	SUBRCUTINE EXAMPL (INFO.LENGTH)	FO		1 2
Č	ILLUSTRATION OF DMATRAM SYNTAX	FO		3
č	IF (INFO.LE-10 .ANC. LENGTH.GT.0)THEN IF (INFO.LE-10 .ANC. LENGTH.GT.0) GO TO 19997 GC TO 19998	DM		5 5 5
17997	CONTINUE CALL CALLER (INFO)	FO	1	5
c	ELSE 60 TO 19999	DM		7
17998	CONTINUE LENGTH=50	FO		7
C	ENC 1F THE REPORT OF THE PROPERTY OF THE PROPE	DM	20	,
C 19999	CONTINUE CASE OF (INFO+6) 19996=INFO+6	DM		9 10 10
alair	60 10 19996	10,98		10
17994	CASE (14)	DM		11
c	LENGTH=LENGTH-INFO CASL (17)	FO	1	12
	GO TO 19995			13
C 17773	CONTINUE DO WHILE (INFO.LT.20)	DM	1	13
17992	CONTINUE IF(INFO.LT.20) 60 TO 19990 GO TO 19991			14
19990	CONTINUE			14
С	GO TG 19987	DM	2	15
19989	IF(LENGTH.LE.INFO) GO TO 19988			15
19987	CONTINUE			15
C	INVUKE (COMPUTE LENGTH) ASSIGN 19985 TO L19985	DM	3	16
	ASSIGN 19986 TO L19985 GO 10 19985			16
19986	CONTINUE			16
C	IF (LENGTH.GE.30) THEN IF (LENGTH.GE.30) GO TO 19982 GO TO 19983	DM	3	17
	CONTINUE	DM		17
С	INVOKE (PRINT-RESULTS). ASSIGN 19980 TO L19980 ASSIGN 19981 TO L19980	-	•	18
19941	GO TO 19980 CCMTINUE			18
C	END IF	DM	3	19
	CONTINUE CONTINUE			19
C	ENC UNTIL GO TO 19989	LM	2	20
17988	CONTINUE	FO		20
c	INFO=INFO+1 END WHILE	DM	2.00	21
19991	GO TO 19992			55
c	CASE ELSE	DM		23
19979	GO TO 19995 CONTINUE			23
C	DO WHILE (LENGTH.GT.0)	DN	1	24
:				

Figure 3.3. Translated FORTRAN

4 DMATRAN CONSTRAINTS

4.1 SYNTAX

- A maximum of 20 cards per statement
- Statement labels between 10000 and 19999 should not be used because the DMATRAN preprocessor adds statement labels, beginning with label 19999 counting backwards, to the FORTRAN source code (Fig. 3.3).
- Don't transfer to labeled DMATRAN statements with FORTRAN
 GO TO's.
- Comments may not be interspersed within DMATRAN statements
- All two-word DMATRAN directives may be written as two separate words or merged into one; i.e., DO UNTIL or DOUNTIL.

4.2 DO UNTIL

When the DO UNTIL...END UNTIL construct is used for iteration, it is important to note that the statements contained within the construct will be executed once before the logical expression is evaluated.

4.3 CASE

The value of <integer-expression> in CASE statements must be positive.

4.4 BLOCK CONSTRUCT

- Each BLOCK...END BLOCK construct should occur after all INVOKE statements which refer to the block name, but may be before or after the RETURN statement.
- Blocks can only be entered through INVOKE statements.
 Sequential control transfers around BLOCK...END BLOCK constructs. Do not use a GO TO enter the middle of a BLOCK..
 END BLOCK construct from outside the block.
- The maximum number of INVOKEs and BLOCKs depends on the lengths of the BLOCK names and number of invocations, see Sec. 2.5.

5 DISPLAY COMMANDS

The DMATRAN precompiler supports a variety of commands for controlling the format of DMATRAN source listings. The capabilities supported include:

- Suppressing source listing
- Double-spacing around comments
- Keyword recognition to allow a more simple DMATRAN syntax
- Page ejection
- Extended comments

5.1 COMMAND FORM

The DMATRAN command statement has two basic forms, both are FORTRAN comment statements and begin with a C in column 1. The first command statement form is

C<command>

<command> must start in column 2 and may be any of the following:

LIST

NOLIST

DSOK

NODS

KWOK

NOKW

EJECT

The second form of the DMATRAN command statement is

CXCOM <value>

<value> must be a single character in column 7; column 6 must be blank.

5.2 SOURCE LISTING

The DMATRAN source listing may be turned off and on with the two commands

CNOLIST

CLIST (default)

This feature is useful when the DMATRAN source code is large and only parts of the code are being modified.

5.3 DOUBLE-SPACE AROUND COMMENTS

Optional double-spacing around comments is obtained by the command

CDSOK

and is turned off with the command

CNODS (default)

5.4 KEYWORD RECOGNITION

The commands for control of display format are:

CKWOK

CNOKW (default)

The CKWOK command (meaning "key-word OK") allows DMATRAN statements to be written in a simpler syntax. When the DMATRAN precompiler is in keyword recognition mode, it recognizes DMATRAN statements which do not have parentheses surrounding clauses (as well as all statements normally recognized). In this mode, DMATRAN keywords are recognized if they begin a statement, contain no blanks, and are immediately followed by a blank. A problem may arise if FORTRAN is the embedded language. FORTRAN IF statements will be interpreted as DMATRAN IF statements when a blank precedes the left parenthesis of the statement. Figure 5.1 contains an example of the simpler DMATRAN syntax with English as the embedded language Figure 5.2 is the listing that results from processing the example in Fig. 5.1 which uses the DMATRAN display commands.

```
CKHOK
     SUBMOUTINE TO FING SQUARE ROOTS
CUSOK
     FOR EACH INFUT VALUE DETERMINE THE SQUARE ROOT
C
      INITIAL VALUE IS POSITIVE. REAL
      DOUNTIL AN EOF IS ENCOUNTERED
      INVOKE REAC INPUT VALUE
     DETERMINE INITIAL ESTIMATE OF SQUARE ROOT
DOWNLE ESTIMATE HAS CONVERGED TO A
      IF CURRENT ESTIMATE IS NORSE THAN PREVIOUS ESTIMATE THEN
      DETERMINE NEW ESTIMATE
      END IF
      END WHILE
      CURRENT EPSILON IS 1.0E-05
C
      IF ESTIMATE ** 2 15 WITHIN EPSILON OF A THEN
      INVOKE PRINT SQUARE HOOT
      ELSE
     INVOKE PRINT ERROR MESSAGE
     END IF
CNOLIST
      THESE BLOCKS WILL BE COCED LATER
      BLOCK REAC INPUT VALUE
      END BLOCK
      BLOCK PRINT ERROR MESSAGE
      END BLOCK
CLIST
CLJECT
CNODS
CNOKW
      BLOCK WRITTEN 6/77
      BLOCK (PRINT SQUARE ROCT)
      PRINT 1000, ROOT
 PRINT 1000, ROOT = *.E12.5)
      RETURN
      ENC
```

Figure 5.1. DMATRAN Keyword Syntax

```
SEQ NEST SOURCE
                   KNOK
         CKHOK
               SUBROUTINE TO FIND SQUARE ROOTS
  2
         COSOK
               FOR EACH INPUT VALUE DETERMINE THE SQUARE ROOT
  5
               INITIAL VALUE IS POSITIVE, REAL
               DOUNTIL AN EOF IS ENCOUNTERED
                   INVOKE READ INPUT VALUE
DETERMINE INITIAL ESTIMATE OF SQUARE ROOT
DOWNILE ESTIMATE HAS CONVERGED TO A
  7
  8
  9
               . . IF CURRENT ESTIMATE IS MORSE THAN PREVIOUS ESTIMATE THEN
 10
                           DETERHINE NEW ESTIMATE
 12
                       END IF
    2
 13
                   END WHILE
                   CURRENT EPSILON IS 1.0E-05
         C
 14
    1
                   IF ESTIMATE**2 IS WITHIN EPSILON OF A THEN
. INVOKE PRINT SQUARE ROOT
 15
16
    2
                       INVOKE PRINT ERROR MESSAGE
 17
18
                   END IF
 19
 20
               END UNTIL
 27
         C
```

```
SEQ NEST SOURCE
                        KHOK
28
29
        CNODS
30
        CNOKH
             BLOCK MRITTEN 6/77
BLOCK (PRINT SQUARE ROOT)
31
        C
32
33
                  PRINT 1806, ROOT
                  FORMAT (* ROOT = *, E12.5)
34
35
              END BLOCK
36
              RETURN
37
              END
```

Figure 5.2. Listing of DMATRAN Keyword Example

5.5 PAGE EJECTION

Specification of page ejection at any point in the DMATRAN listing is especially useful in delineating BLOCK structures; it is obtained by the command

CEJECT

5.6 EXTENDED COMMENT

Comments may follow a statement by using the command

CXCOM <value>

For example, in the command

CXCOM ;

the extended comment character is considered to be ";". The statement

T = T + DT ; ADVANCE TIME

would appear on the DMATRAN listing unmodified, but the text "ADVANCE TIME" would be changed into a FORTRAN comment on the translated FORTRAN output.

C ADVANCE TIME

T = T + DT

APPENDIX A

SUMMARY OF DMATRAN STATEMENTS AND COMMANDS.

SUMMARY OF DMATRAN STATEMENTS AND COMMANDS

PAGE	DMATRAN STATEMENT	FUNCTION
2-3	IFTHENELSEEND IF	Selection construct
2-5	DO WHILEEND WHILE	Iteration with test at top
2-5	DO UNTILEND UNTIL	Iteration with test at bottom
2-8	CASE OFCASECASE ELSEEND CASE	Selection construct
2-11	INVOKE	Execute an internal subroutine
2-11	BLOCKEND BLOCK	Internal subroutine with mnemonic name
PAGE	DMATRAN COMMAND (defaults underlined)	FUNCTION
5-2	LIST	Resume listing of DMATRAN source statements
5-2	NOLIST	Suppress listing of DMATRAN source statements
5-2	DSOK	Double-space around comments
5-2	NODS	Suppress double-spacing around comments
5-2	KWOK	Enter keyword recognition mode
5-2	NOKW	Leave key word recognition node
5-5	EJECT	New page
5-5	XCOM <char></char>	Set the extended comment character

APPENDIX B

FILE DESCRIPTIONS

进州州 医红空

FILES USED AT RADC INSTALLATION

UNIT	FILE NAME	DESCRIPTION
1	INPUT	DMATRAN source input
2	PRINT	Indented listing of DMATRAN source
3	COMPILE	Compilable FORTRAN output

FILES USED AT DMA INSTALLATIONS

UNIT	FILE NAME	DESCRIPTION
5	INPUT	DMATRAN source input
6	PRINT	Indented listing of DMATRAN source
3	COMPILE	Compilable FORTRAN output

APPENDIX C

JOB STREAMS

RADC HONEYWELL 6180/GCOS

SAMPLE DMATRAN JOB STREAM

The job stream in the following example can be used to execute the DMATRAN precompiler.

1.	\$ IDENT			
2.	\$ SELECT	BFCBGRC4/DMATRAN/EXECUTE		
3.	\$ PRMFL	01,R,S,(BCD dmatran source file)		
4.	\$ PRMFL	03,W,S, (BCD translated FORTRAN source file)		
5.	\$ ENDJOB			

The BCD DMATRAN Source File may have been generated by a programmer or by the FAVS Restructure Option (See FAVS User's Guide, General Research Corporation CR-1-754).

RADC HONEYWELL 6180/MULTICS SAMPLE DMATRAN JOB STREAM (USING THE GCOS ENCAPSULATOR)

In order to use the DMATRAN precompiler, using source code written in DMATRAN generated by a programmer or by FAVS restructurer, the job stream shown in the following example can be used.

1. \$ snumb (number) 2. \$ ident 3. \$ program rlhs 4. limits (CP time limit), 32k,, (print line limit) 5. prmf1 h*,r,r,>udd>3201c0320>Urban>dmatran>hstar 6. \$ select >udd>3201c0320>Urban>dmatran>filedefs -ascii 01,r,s,>udd>(BCD dmatran source file) 7. prmf1 8. \$ prmf1 03,w,s, >udd > (BCD Translated FORTRAN source file) 9. \$ endjob

DMA UNIVAC 1100/42 SAMPLE DMATRAN JOB STREAM

The job stream in the following example can be used to execute the DMATRAN precompiler.

@ASG,A	YOURSOURCE.	.YOUR DMATRAN SOURCE	
@USE	Y., YOURSOURCE.		
@ASG,A	DBM*FAVS-DMA.	.ASG DMATRAN PRECOMPILER	
CUSE	DMA.,DBM*FAVS-DMA.	BOSENS AND AND CT 1882 TO SEE	
EXQT	DMA. TRAN	.EXECUTE DMATRAN PRECOMPILER	
@ADD	Y. ELEMENTS	.ADD DMATRAN SOURCE ELEMENTS HERE	

The UNIVAC 1100/42 installation of the DMATRAN precompiler supports an additional command (see Sec. 5.1) to assist in compiling translated DMATRAN. This command contains CFOR in columns 1 thru 4, followed by any desired information in columns 5 thru 80. The DMATRAN precompiler changes the C in column 1 of all CFOR commands to an @ character as the CFOR command is written to the FORTRAN output file. When the DMATRAN precompiler automatically adds the FORTRAN output file to the runstream, the translated CFOR cards direct the FORTRAN V compiler. Note that to compile a DMATRAN source element, the first line in the element should be a CFOR command. Indented listings without FORTRAN V compilations may be obtained by omitting CFOR commands.

INDEX

	PAGES
Automatic Indentation	3-2
BLOCK Construct	2-11, 4-1
BLOCK, Examples	2-12, 2-15
BLOCKs, Maximum Number of	2-13
BLOCK Name	2-11, 2-13
Card, Maximum Number per Statement	4-1
CASE Construct	2-8, 4-1
CASE, Examples of	2-9, 2-10
COMMENTS	5-1, 5-2
Depth, Nesting	3-2, 3-3
Display Commands	5-1
DMA Files	B-2
DMA Job Streams DMATRAN	C-4
Commands	5-1
Constructs	2-1
Guidelines	4-1
Input	3-1
Output	3-2, 3-3
DO UNTIL Construct	2-5, 4-1
DO UNTIL, Examples of	2-7
DO WHILE Construct	2-5
DO WHILE, Examples of	2-6
DSOK Command	5-2, 5-3, 5-4
ELSE	2-3
EJECT Command	5-5
Files	
DMA	B-2
RADC	B-2
IFTHEN construct	2-3
IF()THEN, Examples of	2-3, 2-4
INVOKE, Examples of	2-12, 2-15
INVOKE, Number of	2-13
INVOKE Statement	2-11, 4-1
JOB Streams	
DMA UNIVAC 1100/42	C-4
RADC HONEYWELL 6180/GCOS	C-2
RADC HONEYWELL 6180/MULTICS	C-3

INDEX CONT.

	PAGES
KWOK Command	5-2, 5-3, 5-4
Label, Initial Generation of	4-1
Level, Nesting	3-2, 3-3
LIST Command	5-2, 5-3, 5-4
Listing, FORTRAN	3-3
Listing, DMATRAN	3-2
Listing Unit, DMATRAN	B-2
Nesting Depth	3-2, 3-3
NODS Command	5-2, 5-3, 5-4
NOKW Command	5-2, 5-3, 5-4
NOLIST Command	5-2, 5-3, 5-4
Number of BLOCKs	2-13
Number of INVOKEs	2-13
RADC Files	B-2
RADC Job Streams	C-2, C-3
Structured Programming	1-1
XCOM Command	5-5

DMATRAN CONTROL CONSTRUCTS

CONDITIONAL			
IF (logical expr	ession) THEN	CASE OF (integer expression)	
		{CASE (index {, index})}	
[ELSE]			
		[CASE ELSE]	
END IF			
		END CASE	
LOOP			
DO WHILE (logica	1 expression)	DO UNTIL (logical expression)	
END WHILE		END UNTIL	
SEQUENTIAL			
INVOKE (block na	me)		
BLOCK (block nam	e)		
END BLOCK			
END BLOCK			
	= optional		
		rary number of times	
	DMATRAN COMMANDS	(Defaults Underlined)	
LIST	List source state		
NOLIST	Suppress listing of source statements		
DSOK Double-space aro			
NDOS KWOK	Single-space arou	ind comments identify DMATRAN statements	
NOKW	No reserved keywords		
EJECT	New page		
XCOM <char></char>		comment character	
Cilar	-DE CITO CARCUIACA		